

Berry Bliss Twist Ear Warmer



Copyright © Ambassador Crochet/Kristine Mullen Designs. 01-24-20
Reproducing or transmitting this pattern by any means for any purpose other than for personal use
constitutes a violation of copyright law.

Finished Sizes:

- Toddler – 3 ¼” wide x 16-18” circumference
- Child – 3 ½” wide x 18-20” circumference
- Adult – 4 ¼” tall x 20-22” circumference

Yarn: #4 worsted weight – 1.25 (2, 2.25) oz.

- Samples used Red Heart Super Saver Ombre

Crochet Hook: Size I/5 (5.5 mm)

Notions: Yarn Needle

Gauge:

- 5 v-sts = 4”
- 5 puff st/sc combos = 4”
- 8 rows= 4” in pattern

Special Stitches:

- **Puff stitch** - yo, insert hook in indicated st, yo, pull up loop, [yo, insert hook in same st, yo, pull up a loop] 4 times (11 loops on hook), yo, draw through all 11 loops.
- **V-stitch** – (dc, ch 1, dc) in indicated st or space.

Notes: Pattern is written in toddler size, with child and adult sizes in parentheses. By making ear warmer 2 inches smaller than head circumference it will be less likely to stretch out and get too big.

Abbreviations

ch – chain

dc – double crochet

sl st – slip stitch

sc – single crochet

v-st – v-stitch

yo – yarn over

For a full list of abbreviations, please see my [List of Abbreviations](#).

Ear Warmer

Ch 13 (16, 19),

Row 1: V-st in 5th ch from hook (skipped 4 chs counts as dc and skipped ch 1), *sk next 2 ch, v-st in next ch, rep from * across to last 2 ch, sk next ch, dc in last ch, turn. (3, 4, 5 v-sts, 2 dc)

Row 2: Ch 1 (does not count as st), sc in first st, *puff st in ch-1 sp, ch 1, sk next dc**, sc in next dc, rep from * across ending last rep at **, sc in top of beg ch-3, turn. (3, 4, 5 puff sts, 4 sc)

Row 3: Ch 1 (does not count as st), dc in 1st sc, *sk ch-1 sp, v-st in top of puff st, sk sc, rep from * across, dc in last sc, turn. (3, 4, 5 v-sts)

Row 4: Ch 1, sc in first st, *puff st in ch-1 sp, ch 1, sk next dc**, sc in next dc, rep from * across ending last rep at **, sc in last dc, turn. (3, 4, 5 puff sts, 4 sc)

Rows 5 – 31 (35, 37): Rep Rows 3 & 4, or until ear warmer measures approx. 15½ (17, 18)'' long. (For larger adult head add 1-2'' - see Notes on sizing)
Fasten off, leaving 12'' tail for sewing.

Finishing

Fold both short ends in half (into a C shape) and put each end into the fold (see photos below). Sew through all 4 layers.





Copyright © Ambassador Crochet/Kristine Mullen Designs. 01-24-20
Reproducing or transmitting this pattern by any means for any purpose other than for personal use
constitutes a violation of copyright law.